



POLYCOM[®]

KIRK[®] Release Note
KIRK[®] 6020 and KIRK[®] 7010

Firmware Version PCS 05Da
Q2/2010

Table of Contents

1. INTRODUCTION.....	1
1.1 TARGET GROUPS.....	1
1.2 TERMS AND DEFINITIONS.....	1
2. GENERAL.....	1
3. IMPORTANT NOTES	1
3.1 UPDATING USB DRIVER	1
3.2 UPDATING HANDSET.....	1
4. DISTRIBUTION FILES	1
5. CHANGES.....	2
5.1 VERSION PCS 05DA (Q2/2010).....	2
5.1.1 <i>Added or Changed Features</i>	2
5.1.2 <i>Removed Features</i>	2
5.1.3 <i>Corrections</i>	2

1. Introduction

1.1 Target Groups

Partners and distributors.

1.2 Terms and Definitions

HMP Handset Management KIRK 50-, 60- and 70- series V 1.00

2. General

This combined release note describes the KIRK 6020 add KIRK 7010 handset. The basic functionality is the same for these handsets except that KIRK 7010 has reduced functionality (no vibrator, headset connector, hands free and LED on top).

This release note applies to firmware PCS 05Da. It replaces beta build PCS 05Ca.

3. Important Notes

3.1 Updating USB Driver

The Device Manager/USB Serial Port/Driver/Driver Version should be 2.6.0.0 or later.

Otherwise download and install the Vista and WHQL Certified USB “setup executable” from this location:

<http://www.ftdichip.com/Drivers/VCP.htm>

NB: Disconnect the USB connector before updating the driver.

3.2 Updating Handset

Before upgrading back up the phonebook and/or settings, using the HMP.



If you upgrade a handset prior to version PCS 05Ca, you must activate the default factory settings.

4. Distribution Files

14179910_05Da.hsx (Firmware image for KIRK 6020 handset).

14179940_05Da.hsx (Firmware image for KIRK 7010 handset).

5. Changes

5.1 *Version PCS 05Da (Q2/2010)*

5.1.1 Added or Changed Features

- The handset will turn itself off after five minutes, if it has not been subscribed to a system. This feature is added to avoid battery discharge, if the handset is accidentally turned on during transportation.

5.1.2 Removed Features

5.1.3 Corrections

- To avoid unpredictable behavior of the handset, it will not turn on if battery level is low. The LED* at top will light red while the power key is pressed.

* Not available in KIRK 7010